

## Assessment Evaluation Checklist

### Basic Setup

- 1. Install the Stratusphere Hub virtual appliance**  
*OVF, VMDK and XVA downloads from [www.liquidwarelabs.com](http://www.liquidwarelabs.com), install on host, run quickstart in console to assign network address*
- 2. Enable Connector ID Key software for target desktops and users**  
*Login to Administration module at [https://\[hub-ip-address\]](https://[hub-ip-address]) default account ssadmin/sspassword, go to CMDB Administration > Connector ID Keys software tab, get local or network install*
- 3. Confirm that Connector ID Keys are communicating with the Hub**  
*Login to Stratusphere Fit, check Dashboard showing data, go to Inventory > Machines and check that all desktops are showing up and that Last Contact Date is updating regularly*
- 4. Set Connector ID Keys to auto-delete when assessment period is over**  
*Login to Administration, go to CMDB Administration > Connector ID Keys properties, select “Automatically uninstall Connector ID Key software” and set to “after X days”*

### Key Assessment Features

- 1. Dashboard with overview of assessment progress and key metrics**  
*Login to Stratusphere Fit, see dashboard with summary header, click on widget Inspect links*
- 2. One-click summary Powerpoint report, customizable as project deliverable**  
*Login to Stratusphere Fit, click “Generate Summary Report”, select start date and end date of assessment, summary powerpoint is generated and stored in the report archives*
- 3. Configurable VDI Fit assessment rating system**  
*Login to Stratusphere Fit, go to Assessment > VDI Fit Profiles, view or change targets, thresholds, and weightings of profile, see overall rating results in Insepector > VDI Fit Scatter Plot*
- 4. Ability to import and create user groups and machine groups for analysis**  
*Login to Administration, go to CMDB Administration > User Directories where you can import groups using CSV or from AD/LDAP, go to Inventory where you can manually setup groups*
- 5. Automatic inventory of Machines, Users, and Applications**  
*Login to Stratusphere Fit, go to Inventory, look at Machines, Users, and Desktop Applications, for machines select individual rows and click Edit button to see full configuration details*
- 6. Detailed data on configurations, workloads, and network latency**  
*Login to Stratusphere Fit, go to Assessment > Inspector, run Machine Configuration Charts, Resource Utilization Charts, and other views, go to Reports and click on Report Library, see list of available reports, select individual reports and click Run button to execute the reports*
- 7. Identify targets for application virtualization, with key resource requirements**  
*Login to Stratusphere Fit, go to Assessment > Reports, click on Report Library, select and run the Application Inventory, Application Usage Summary and Application Virtualization Targets reports*
- 8. Identify targets for desktop virtualization, with key resource requirements**  
*Login to Stratusphere Fit, go to Assessment > Reports, click on Report Library, select and run the VDI Fit by Machine, VDI Fit by User, and VDI Design Baseline reports*

*For more information on installation, features and functionality, as well as post-assessment capabilities, see the Stratusphere Assessment Evaluation Guide and other product documentation.*